

Configuring Security Policy Engine for SESM

This chapter describes how to configure the Security Policy Engine (SPE) component to work with SESM applications. The chapter includes the following topics:

- SPE Attributes, page 8-1
- Extending the Directory Schema and Loading Initial RBAC Objects, page 8-3
- Loading Sample Data, page 8-4

SPE Attributes

SPE uses the following MBeans:

- Directory MBean, page 8-2
- Connection MBeans, page 8-3—Two connection MBeans might be configured:
 - Connection MBean, instance=Primary
 - Connection MBean, instance=Secondary

The SPE MBeans are used by any application that incorporates the SPE, which could include SESM portals deployed in LDAP mode, the RDP server, and the CDAT application. Each application has its own version of SPE MBeans.

To change attributes in the SPE MBeans, you can either:

• Edit the SPE MBean configuration file in the appropriate SESM application config directory:

```
applicationName
config
dessauth.xml
```

Make changes using the Agent View for an application that incorporates SPE APIs.



The SPE component does not have its own management console. Rather, the SPE MBeans are managed from the application's MBean list, on the application's management console.

Directory MBean

The Directory MBean configures logging and caching attributes for executing classes in the SPE APIs. Table 8-1 describes the attributes in the Directory MBean.

Table 8-1 SPE—Directory MBean

Attribute Name	Explanation
connectionNameRoot	Root name of the individual connection Mbeans. This MBean searches for other mbeans that begin with this name and assumes that those MBeans are connections to the directory.
factory	Do not change the installed value.
context	Default LDAP context. This is the organization and organizational unit that was created to hold the SESM data.
DESSPrincipal	Name used to connect to the SESM organization and organization unit. This user must have permission to create objects in the SESM context.
alwaysGetAllAttributes	If set to true, all the attributes of an LDAP entry are returned for each query.
traceFileName	Name of the directory log file.
traceLevel	Should be one of: NONE, ERROR, BRIEF, VERBOSE, or DEBUG.
printTraceToConsole	If set to true, the application sends trace messages to the console and writes them into the log file.
stackTrace	If set to true, the application prints a stack trace with each trace message.
cacheMaxObjects	Specifies the maximum number of software objects to hold in the cache. Objects represent subscribers, services, privileges, roles, and so on.
	When the cache contains cacheMaxObjects, old objects are deleted from cache, regardless of available cache space. Set this value high to allow the available cache space to be the determining factor for cache management.
	Installed default: 50000
cacheMinFreeMem	Specifies the percentage of Java virtual memory that must remain available (that is, not used by the cache) after the application is loaded into memory.
	You can calculate the specific amount of memory available for the cache as follows:
	cacheSize = (JavaVirtualMemory- applCodeSize) * (100% - cacheMinFreeMem)
	Where:
	JavaVirtualMemory is the maximum virtual memory size specified at application startup time with the jvm argument. The installed startup scripts use the following values:
	• The startNWSP script uses 64 MB
	• The runrdp script uses 20 MB
	applCodeSize is the application size. The NWSP is approximately 18 MB.
	<i>cacheMinFreeMem</i> is the percentage of JVM that must remain available after the application is loaded into memory.
	For example, the <i>cacheSize</i> for NWSP is 90% of 14 MB, or 12.6 MB:
	cacheSize = (32 MB - 18 MB) * (100% - 10%)
	Default: 10

Attribute Name	Explanation
cacheSessionTimeout	Specifies the timeout of inactive client sessions in seconds.
	Default: 600
cacheExpireInterval	Specifies the interval in seconds after which the cache attempts to expire objects.
	Note Do not set this attribute to 0. A value of 0 causes <i>every</i> request to go to the directory, bypassing caching and any memory storage from a recent request for the same object. A value of 0 degrades performance substantially.
	Default: 600
cacheObjectTimeout	Specifies the number of seconds before objects time out.
	Default: 600

Table 8-1 SPE—Directory MBean (continued)

Connection MBeans

The Connection MBeans configure location and security attributes required to connect to an LDAP directory. If you configure and deploy two LDAP directories for failover protection, make sure to configure two instances of the connection MBean, using the appropriate connection information for the primary and secondary directories. The connection MBean names are:

- Connection, instance=Primary
- Connection, instance=Secondary

Table 8-2 describes the attributes in the Connection MBeans.

Table 8-2	SPE—Connection MBeans
	c: _ cc:cc:

Attribute Name	Explanation
poolSize	Number of active connections allowed to the LDAP server.
URL	URL of the LDAP server.
principal	Name used when connecting to the LDAP server.
credentials	Credentials (such as password) used for connecting to the LDAP server.

Extending the Directory Schema and Loading Initial RBAC Objects

For SESM deployments running in LDAP mode, you must make the following modifications on the LDAP directory:

- Extend the directory schema—These extensions include the dess and auth classes and attributes that will hold the SESM data. For more information about the extensions, see the *Cisco Distributed Administration Tool Guide*.
- Load initial RBAC objects—Some initial top-level rules and roles must be created in the directory before an administrator can log into CDAT and create additional objects.

The SPE installation process optionally performs these update activities. If you did not choose these options during installation, you must perform these updates before running CDAT or SESM applications in LDAP mode.

To perform these updates after SESM installation, use either of the following procedures:

- Perform a custom SESM installation, installing just the SPE component, to make the updates. See the following section "Rerunning the SESM Installation to Update the Schema and Load RBAC **Objects**" for instructions.
- ٠ Perform the updates manually using native administration tools and commands. See the following file in the SESM installation directory for instructions:

```
dess-auth
   schema
      README.SESM.LDIF.html
```

Rerunning the SESM Installation to Update the Schema and Load RBAC Objects

To use the SESM custom installation process to extend the directory schema and load initial RBAC objects, follow these procedures:

Step 1	Make sure the LDAP directory server is running.
•	· C

_ _ . _ ..

- Step 2 Make sure you know the following user IDs and passwords:
 - A user ID and password that allows you to update the directory schema
 - A user ID and password that allows you to update the container (organization and organizational unit) that you created for SESM data.
- Step 3 Execute the SESM installation program on a server that has network access to the LDAP directory.
- When the installation program prompts for setup type, choose Custom. Step 4
- Step 5 When the installation program prompts for the components to install, choose SPE.
- When the installation program prompts for directory connection information, provide correct Step 6 information to access the directory. This includes the names of the organization and organizational unit you created to hold the SESM data.
- When the installation program displays the options, click Update schema and Install RBAC. Step 7

Loading Sample Data

The SESM installation includes sample data that you can optionally load into the LDAP directory, after the SPE extensions are applied. The sample data is located in:

```
dess-auth
   schema
       samples
           DESSusecasedata.ldf
```

To load the sample data, follow instructions in the following file:

```
dess-auth
   schema
       README.SESM.LDIF.html
```

Cisco Subscriber Edge Services Manager Installation and Configuration Guide